



OpenVPN Configuration

Server Configuration

OpenVPN server configuration typically resides in `/etc/openvpn/server.conf` or a similar path. Here's a basic configuration example:

```
port 1194
proto udp
dev tun
ca /etc/openvpn/easy-rsa/pki/ca.crt
cert /etc/openvpn/easy-rsa/pki/issued/server.crt
key /etc/openvpn/easy-rsa/pki/private/server.key
dh /etc/openvpn/dh.pem
server 10.8.0.0 255.255.255.0
ifconfig-pool-persist ipp.txt
push "redirect-gateway def1 bypass-dhcp"
push "dhcp-option DNS 8.8.8.8"
push "dhcp-option DNS 8.8.4.4"
keepalive 10 120
comp-lzo
persist-key
persist-tun
status openvpn-status.log
log-append openvpn.log
verb 3
```

Key Parameters:

- `port`: The port OpenVPN listens on.
- `proto`: Protocol used (UDP or TCP).
- `dev`: Tunnel device (tun or tap).
- `ca`, `cert`, `key`: Paths to CA certificate, server certificate, and private key.
- `dh`: Diffie-Hellman parameters.
- `server`: VPN subnet and netmask.
- `push`: Options pushed to clients (e.g., DNS servers, gateway redirection).

Client Configuration

Client configuration files (e.g., `client.conf`) define how clients connect to the OpenVPN server:

```
client
dev tun
proto udp
remote your_server_ip 1194
resolv-retry infinite
nobind
persist-key
persist-tun
ca ca.crt
cert client.crt
key client.key
comp-lzo
verb 3
```

Key Parameters:

- `client`: Specifies this is a client configuration.
- `remote`: Server IP address and port.
- `ca`, `cert`, `key`: Paths to client certificates and keys.

Starting and Stopping OpenVPN

Start OpenVPN server:

```
``bash
systemctl start openvpn@server
``
```

Stop OpenVPN server:

```
``bash
systemctl stop openvpn@server
``
```

Check OpenVPN status:

```
``bash
systemctl status openvpn@server
``
```

WireGuard Configuration

Server Configuration

WireGuard configurations are typically located in `/etc/wireguard/wg0.conf` (for the `wg0` interface). Example server configuration:

```
[Interface]
PrivateKey = <server_private_key>
Address = 10.6.0.1/24
ListenPort = 51820
PostUp = iptables -A FORWARD -i wg0 -j ACCEPT; iptables -t nat -A POSTROUTING -o eth0 -j MASQUERADE
PostDown = iptables -D FORWARD -i wg0 -j ACCEPT; iptables -t nat -D POSTROUTING -o eth0 -j MASQUERADE

[Peer]
PublicKey = <client_public_key>
AllowedIPs = 10.6.0.2/32
```

Key Parameters:

- `PrivateKey` : Server's private key.
- `Address` : Server's IP address in the VPN subnet.
- `ListenPort` : Port WireGuard listens on.
- `PostUp`, `PostDown` : Commands to execute when the interface is brought up or down (e.g., iptables rules).
- `PublicKey` : Client's public key.
- `AllowedIPs` : IP addresses allowed for the client.

Client Configuration

Example client configuration:

```
[Interface]
PrivateKey = <client_private_key>
Address = 10.6.0.2/32
DNS = 8.8.8.8, 8.8.4.4

[Peer]
PublicKey = <server_public_key>
Endpoint = your_server_ip:51820
AllowedIPs = 0.0.0.0/0
PersistentKeepalive = 25
```

Key Parameters:

- `PrivateKey` : Client's private key.
- `Address` : Client's IP address in the VPN subnet.
- `DNS` : DNS servers to use.
- `PublicKey` : Server's public key.
- `Endpoint` : Server IP address and port.
- `AllowedIPs` : IP ranges allowed via the VPN.
- `PersistentKeepalive` : Interval to send keepalive packets.

Starting and Stopping WireGuard

Bring up WireGuard interface:	```bash wg-quick up wg0 ````
Bring down WireGuard interface:	```bash wg-quick down wg0 ````
Check WireGuard status:	```bash wg show wg0 ````

IPsec Configuration

IKEv2 Configuration (Strongswan)

Strongswan is a popular IPsec implementation. Configuration files are usually located in `/etc/ipsec.conf` and `/etc/ipsec.secrets`.

`/etc/ipsec.conf` example:

```
config setup
    charondebug="ike 1, knl 1, cfg 0"

conn ikev2-vpn
    auto=add
    keyexchange=ikev2
    ike=chacha20poly1305-sha512-curve25519!
    esp=chacha20poly1305-sha512!
    dpdaction=clear
    rekey=no
    left=%any
    leftid=@your_server_id
    leftcert=server.pem
    leftsubnet=0.0.0.0/0
    right=%any
    rightid=%any
    rightauth=eap-mschapv2
    rightsourceip=10.1.0.0/24
    eap_identity=%identity
```

`/etc/ipsec.secrets` example:

```
: RSA serverKey.pem
username : EAP "password"
```

Key Parameters:

- `left` : Local endpoint configuration (server).
- `right` : Remote endpoint configuration (client).
- `leftid` : Server identifier.
- `rightid` : Client identifier.
- `leftcert` : Server certificate.
- `rightauth` : Client authentication method (e.g., EAP-MSCHAPv2).
- `rightsourceip` : IP address pool for clients.

Starting and Stopping IPsec (Strongswan)

Start IPsec service:
``bash
systemctl start ipsec
``

Stop IPsec service:
``bash
systemctl stop ipsec
``

Restart IPsec service:
``bash
systemctl restart ipsec
``

Check IPsec status:
``bash
ipsec status
``

Troubleshooting VPN Connections

Common Issues and Solutions

Connectivity Problems:

- **Firewall Issues:** Ensure VPN traffic is allowed through firewalls (e.g., ports 1194 for OpenVPN, 51820 for WireGuard, 500/4500 for IPsec).
- **Routing Problems:** Verify that the routing is configured correctly, especially if using VPN for specific subnets.
- **Incorrect IP Addresses:** Double-check server and client IP configurations.

Authentication Failures:

- **Certificate Issues:** Verify that certificates are valid and correctly configured on both the server and client.
- **Incorrect Credentials:** Ensure that usernames and passwords are correct.

DNS Resolution Issues:

- **DNS Configuration:** Ensure that VPN clients are using the correct DNS servers (e.g., pushed via OpenVPN or configured in WireGuard).
- **DNS Leaks:** Test for DNS leaks to ensure that DNS queries are going through the VPN.

Debugging Tools

Ping:
```bash  
ping  
````

Traceroute:
```bash  
traceroute  
````

Tcpdump:
```bash  
tcpdump -i port  
````

Netstat/Ss:
```bash  
netstat -tulnp  
ss -tulnp  
````