



Basic Navigation

Core Keybindings

<code>SPC</code>	Opens the Spacemacs key guide, your primary interface.
<code>SPC h</code> <code>d k</code>	Describe key. Shows what a key does.
<code>SPC h</code> <code>d f</code>	Describe function. Shows information about a function.
<code>SPC h</code> <code>d v</code>	Describe variable. Shows information about a variable.
<code>SPC h</code> <code>t k</code>	Find a key from a string
<code>SPC h</code> <code>SPC</code>	Show all spacemacs commands.

Basic Movement

<code>j</code>	Move cursor down one line.
<code>k</code>	Move cursor up one line.
<code>h</code>	Move cursor left one character.
<code>l</code>	Move cursor right one character.
<code>C-f</code>	Move forward one screen.
<code>C-b</code>	Move backward one screen.

Editing Basics

<code>i</code>	Insert mode: insert before cursor.
<code>a</code>	Insert mode: insert after cursor.
<code>o</code>	Insert mode: open a new line below.
<code>d</code>	Delete under cursor.
<code>x</code>	Delete character under cursor.
<code>u</code>	Undo.

File Management

File Operations

<code>SPC f f</code>	Find file (open file).
<code>SPC f s</code>	Save file.
<code>SPC f S</code>	Save all files.
<code>SPC f c</code>	Copy file.
<code>SPC f D</code>	Delete file.
<code>SPC f r</code>	Rename file.

Buffer Management

<code>SPC b n</code>	Next buffer.
<code>SPC b p</code>	Previous buffer.
<code>SPC b d</code>	Delete buffer (close).
<code>SPC b b</code>	Switch to buffer.
<code>SPC b k</code>	Kill current buffer.
<code>SPC b r</code>	Revert buffer (reload from file).

Configuration Files

<code>SPC f e d</code>	Edit dotfile configuration.
<code>SPC f e R</code>	Reload configuration.
<code>SPC f e s</code>	Open .spacemacs file.
<code>SPC h r r</code>	Reload theme.

Window Management

Window Selection

<code>SPC w h</code>	Select window left.
<code>SPC w j</code>	Select window below.
<code>SPC w k</code>	Select window above.
<code>SPC w l</code>	Select window right.

Window Manipulation

<code>SPC w H</code>	Move window left.
<code>SPC w J</code>	Move window down.
<code>SPC w K</code>	Move window up.
<code>SPC w L</code>	Move window right.
<code>SPC w s</code>	Split window horizontally.
<code>SPC w v</code>	Split window vertically.

Other Window Commands

<code>SPC w</code> <code>c</code>	Close current window.
<code>SPC w</code> <code>o</code>	Only keep current window (delete others).
<code>SPC w</code> <code>=</code>	Balance window sizes.
<code>SPC w</code> <code>t</code>	Toggle window dedicated mode.

Project Management

Project Switching

<code>SPC p l</code>	Switch to last project.
<code>SPC p p</code>	Switch to project (ivy).
<code>SPC p f</code>	Find file in project.
<code>SPC p h</code>	Open files and recent.

Project Tools

<code>SPC p t</code>	Show project tree.
<code>SPC p '</code>	Open project terminal.
<code>SPC p \$ t</code>	Open terminal in project root.
<code>SPC p g</code>	Project-related git commands.

Search and Replace

<code>SPC s s</code>	Search in current buffer.
<code>SPC s p</code>	Search in project.
<code>SPC s r</code>	Replace in current buffer.
<code>SPC s R</code>	Replace in project.